



3500 CORPORATE PARKWAY
CENTER VALLEY, PA 18034-0610
DIGITAL TECHNICAL SUPPORT
CONSUMER PRODUCTS GROUP
(888) 553-4448
<http://support.olympusamerica.com>

DSS Player for Mac Software Update V7.10

Description:

This software update module (DSSPlayer710.DMG) applies to DSS Player for Mac V7 versions.

System Requirements

The minimum System requirements to operate the DSS Player for MAC V7 are shown below.

Item	Condition
OS	Mac OS X 10.3.9 or later
CPU	Power PC G3 500MHz or better Intel Core Solo / Duo 1.5GHz or better
Memory	256MB or more
Disk space of HDD	200MB or more
Drive	CD drive
Display	1024 x 768 dot or more 32,000 colors or more
USB port ^{*1}	One or more available
Audio input/output	Earphone, or speaker output
Others	Safari 1.0 or later, QuickTime 7 or later Flip4Mac(WMA playback) ^{*2}

*1 : Operation will not be guaranteed when expansion USB port is used.

*2 : When Windows Media® Components for QuickTime, Flip4Mac™, is installed you can directly play the WMA file with the DSS Player. You can use WMA file playback function free of charge. For further information, please refer to the Flip4Mac web site.

Software Enhancements:

OS	Change	Description
OSX	Improvement	Support DS-5000 barcode firmware v1.04
OSX	Bug	Verbal Comment recording functions continue to work (F1 button) even after the options has been disabled.
OSX	Bug	DSS/DS2 files, which have been edited on a DS-5000, will not play in DSS Player for MAC.



3500 CORPORATE PARKWAY
CENTER VALLEY, PA 18034-0610
DIGITAL TECHNICAL SUPPORT
CONSUMER PRODUCTS GROUP
(888) 553-4448
<http://support.olympusamerica.com>

Installation Instructions:

1. Click the **DSS Player for Mac Update V7.10** link to start the download.
2. Save the file to your hard disk.
3. Close all open programs.
4. Double-click the DSSPlayer710.DMG file on your hard disk to open the disk image.
5. Double-click the **DSS Player (MAC) Updater X**
6. Follow the instructions on the screen to complete the installation.