



DSS Player for Mac Software Upgrade V6 to V7

Description:

This software upgrade module (DSSPlayer701.DMG) applies to all DSS Player for Mac V6 versions.

System Requirements

The minimum System requirements to operate the DSS Player for MAC V7 are shown below.

Item	Condition
OS	Mac OS X 10.3.9 or later
CPU	Power PC G3 500MHz or better Intel Core Solo / Duo 1.5GHz or better
Memory	256MB or more
Disk space of HDD	200MB or more
Drive	CD drive
Display	1024 x 768 dot or more 32,000 colors or more
USB port ^{*1}	One or more available
Audio input/output	Earphone, or speaker output
Others	Safari 1.0 or later, QuickTime 7 or later Flip4Mac(WMA playback) ^{*2}

*1 : Operation will not be guaranteed when expansion USB port is used.

*2 : When Windows Media® Components for QuickTime, Flip4Mac™, is installed you can directly play the WMA file with the DSS Player. You can use WMA file playback function free of charge. For further information, please refer to the Flip4Mac web site.

DSS Player for MAC V7 added functionality (software enhancements)

- Support DS-5000, DS-30/40/50, WS Series, DR-1000/2000
- Support DSS Pro audio format
- Support MP3 files playback
- Noise cancellation
- Tone control
- Channel separation (Only for Plus version)
- Device control when direct recording
- Transfer function of voice guidance file
- Foot Switch customization
- Automatic start when the device is connected

Note : DSS Player for MAC V7 does not support the following discontinued recorders DS-3000/2000/660/330/320/150/10, DM-1 and the RS-25 foot pedal. While direct recording is supported, Direct Recording in DSS LP mode and WMA format are not.



Upgrading to DSS Player for MAC V7

Upgrading DSS Player for MAC V6 to V7 (CD or Upgrade Module)

DSS Player for MAC V6 can be upgraded to DSS Player for MAC V7 free of charge. If you install DSS Player for MAC V7 on a PC that has DSS Player for MAC V6, the software will be upgraded to V7 using the license ID of V6.

[Remarks]

- If V6 Plus Edition is installed, it will be upgraded to Plus Edition of V7.
- If V6 is installed in the default folder (/Applications/DSS Player), it will be overwritten by V7.
- If V6 is installed to a custom folder (none default), installing V7 to the default folder will cause both V6 and V7 to co-exist on the PC. However, the V6 software will not be guaranteed to operate correctly.
- When upgrading to V7, V6 settings will not be transferred to V7 software. All settings in V7 will be set as default.

Upgrading DSS Player for MAC version 1.x to V7 (CD or Upgrade Module)

Upgrading from DSS Player for MAC v1.xx to V7 is not supported. You need to upgrade to V6 first before you can upgrade to V7. If you install DSS Player for MAC V7 on a PC that has DSS player for Mac v1.xx installed, you will need to register the license ID on initial startup, as if it is a new installation.

Installation Instructions:

1. Click the **DSS Player for Mac Upgrade Module V6 to V7** link to start the download.
2. Save the file to your hard disk.
3. Close all open programs.
4. Double-click the DSSPlayer701.DMG file on your hard disk to open the disk image.
5. Double-click the **DSS Player(MAC) Updater X**
6. Follow the instructions on the screen to complete the installation.