



3500 CORPORATE PARKWAY
CENTER VALLEY, PA 18034-0610
DIGITAL TECHNICAL SUPPORT
CONSUMER PRODUCTS GROUP
(888) 553-4448
<http://support.olympusamerica.com>

DSS Player Standard Upgrade Release Note

Description:

When installing DSS Player Standard Upgrade on a PC that has DSS Player V7 installed, the installer will perform the installation successfully by generating a license ID based on the current DSS Player V7 license ID.

System Requirements

- Operating System :
Windows 2000 with SP4, Windows XP with SP1 or later, Windows Vista

Supported Devices

- Olympus Recorder
DS-Series, WS-Series
- Foot Switch
RS-25/26 and RS-27/28

Upgrade Specifics

This upgrade is applicable in the following cases:

- If DSS Player V7 bundled with AS-2300 or Plus version is installed, the upgrade will install DSS Player Standard (**Transcription Module**.)
- If DSS Player V7 bundled with DS-Series recorders or Plus version is installed, the upgrade will install DSS Player Standard (**Dictation Module**.)

Notes:

1. DSS Player V7 will not be uninstalled automatically after upgrade.
2. DSS Player Standard settings are default setting and not necessarily those of V7.

Installation Instructions:

1. Click the **DSS Player V7 Upgrade to Standard** link to start the download.
2. Save the file to your hard disk.
3. Close all open programs.
4. Double-click the zip file on your hard disk to expand its contents.
5. Double-click the DSSStandardUpgrade3.exe program file on your hard disk to start the update program.
6. Follow the instructions on the screen to complete the installation.